

The `pdflscape` package

Heiko Oberdiek*

2019/12/05 v0.12

Abstract

Package `pdflscape` adds PDF support to the environment `landscape` of package `lscape` by setting the PDF page attribute `/Rotate`.

Contents

1 Documentation	2
1.1 Supported drivers	2
1.2 Caveat	2
1.3 Requirements	2
1.4 Usage	2
2 Implementation	2
2.1 Package identification	2
2.2 Driver options	2
2.3 Autodetection of driver	3
2.3.1 Driver <code>pdftex</code>	3
2.3.2 Driver <code>xetex</code>	3
2.3.3 Detect driver based on <code>\Gin@driver</code>	4
2.3.4 Driver <code>dvips</code>	4
2.4 Driver implementation	5
2.4.1 <code>pdfTEX</code>	5
2.4.2 PostScript driver	6
2.4.3 Driver <code>dvipdfm</code>	6
2.5 Driver independent stuff	6
3 Installation	7
3.1 Download	7
3.2 Bundle installation	8
3.3 Package installation	8
3.4 Refresh file name databases	8
3.5 Some details for the interested	8
4 History	9
[2001/01/15 v0.1]	9
[2001/02/04 v0.2]	9
[2004/05/11 v0.3]	9
[2004/05/12 v0.4]	9
[2006/02/20 v0.5]	9
[2006/04/24 v0.6]	9

*Please report any issues at <https://github.com/ho-tex/pdflscape/issues>

[2007/04/11 v0.7]	9
[2007/04/17 v0.8]	9
[2007/10/21 v0.9]	9
[2008/08/11 v0.10]	9
[2016/05/14 v0.11]	10
[2019/12/05 v0.12]	10

5 Index	10
---------	----

1 Documentation

1.1 Supported drivers

- pdftex,lualatex
- dvips, dvipsone, pctex32, pctexps (and other drivers that provide a non-empty `\Gin@PS@raw`)
- dvipdfm

1.2 Caveat

Depending on the configuration Ghostscript adds a guessed rotation entry by its own. This can lead to two `/Rotate` entries per page. To prevent this behaviour set the parameter `AutoRotatePages` to `/None`, eg:

```
ps2pdf -dAutoRotatePages=/None
```

1.3 Requirements

- The package `lscape`.
- The package `atbegshi` for all drivers except `pdftex,lualatex`.

1.4 Usage

Load this package instead of or after package `lscape`:

```
\usepackage{pdflscape}
\begin{landscape}...\end{landscape}
```

2 Implementation

2.1 Package identification

```
1 (*package)
```

Package identification.

```
2 \NeedsTeXFormat{LaTeX2e}
3 \ProvidesPackage{pdflscape}%
4 [2019/12/05 v0.12 Display of landscape pages in PDF (HO)]
```

2.2 Driver options

```
5 \let\PLS@option\empty
6 \let\PLS@driver\empty
7 \def\PLS@temp#1#2{%
8   \DeclareOption{#1}{%
```

```

9      \let\PLS@option\CurrentOption
10     \def\PLS@driver{\#2}%
11   }%
12 }
13 \PLS@temp{pdftex}{pdftex}
14 \PLS@temp{luatex}{pdftex}
15 \PLS@temp{dvips}{dvips}
16 \PLS@temp{dvipsone}{dvips}
17 \PLS@temp{pctexps}{dvips}
18 \PLS@temp{dvipdfm}{dvipdfm}
19 \PLS@temp{dvipdfmx}{dvipdfm}
20 \PLS@temp{xetex}{dvipdfm}
21 \let\PLS@temp\empty
22 \DeclareOption*{%
23   \ifx\PLS@temp\empty
24     \let\PLS@temp\CurrentOption
25   \else
26     \edef\PLS@temp{\PLS@temp,\CurrentOption}%
27   \fi
28 }
29 \ProcessOptions*
30 \ifx\PLS@option\empty
31 \else
32   \expandafter\PassOptionsToPackage\expandafter{\PLS@option}{lscape}%
33 \fi
34 \ifx\PLS@temp\empty
35 \else
36   \expandafter\PassOptionsToPackage\expandafter{\PLS@temp}{lscape}%
37 \fi
38 \RequirePackage{iftex}[2019/11/07]%
39 \RequirePackage{lscape}

```

2.3 Autodetection of driver

2.3.1 Driver pdftex

```

40 \def\PLS@temp{pdftex}
41 \ifpdf
42   \ifx\PLS@driver\empty
43     \let\PLS@driver\PLS@temp
44     \PackageInfo{pdflscape}{Auto-detected driver: \PLS@temp}%
45   \fi
46 \ifx\PLS@driver\PLS@temp
47 \else
48   \PackageError{pdflscape}{%
49     The driver option ‘\PLS@option’ is not compatible\MessageBreak
50     with pdfTeX in PDF mode, using driver ‘pdftex’ instead%
51   }\@ehc
52   \let\PLS@driver\PLS@temp
53 \fi
54 \fi

```

2.3.2 Driver xetex

```

55 \def\PLS@temp{dvipdfm}
56 \ifxetex
57   \ifx\PLS@driver\empty
58     \let\PLS@driver\PLS@temp
59     \PackageInfo{pdflscape}{%
60       Auto-detected driver: \PLS@temp\space(xetex)%

```

```

61      }%
62  \fi
63 \ifx\PLS@driver\PLS@temp
64 \else
65   \PackageError{pdflscape}{%
66     The driver option '\PLS@option' is not compatible\MessageBreak
67     with XeTeX, using driver for XeTeX (dvipdfm) instead%
68   }\@ehc
69   \let\PLS@driver\PLS@temp
70 \fi
71 \fi

```

2.3.3 Detect driver based on \Gin@driver

```

72 \def\PLS@temp#1#2{%
73   \ifx\PLS@driver\@empty
74     \begingroup
75       \def\PLS@temp{#1.def}%
76     \expandafter\endgroup
77   \ifx\PLS@temp\Gin@driver
78     \def\PLS@driver{#2}%
79     \PackageInfo{pdflscape}{%
80       Auto-detected driver: \PLS@driver\space(#1)%
81     }%
82   \fi
83 \fi
84 }
85 \PLS@temp{dvipdfm}{dvipdfm}
86 \PLS@temp{dvipdfmx}{dvipdfm}
87 \PLS@temp{dvips}{dvips}
88 \PLS@temp{dvipsone}{dvips}
89 \PLS@temp{pctexps}{dvips}

```

2.3.4 Driver dvips

```

90 \ifx\PLS@driver\@empty
91   \def\PLS@temp{dvips}%
92   \ifnum 1=0\ifx\Gin@PS@raw\@undefined
93     \else
94       \ifx\Gin@PS@raw\relax
95         \else
96           \ifx\Gin@PS@raw\@empty
97             \else
98               1%
99             \fi
100            \fi
101          \fi
102        \space
103      \let\PLS@driver\PLS@temp
104      \PackageInfo{pdflscape}{%
105        Auto-detected driver: \PLS@temp\space(PostScript)%
106      }%
107    \fi
108 \fi
109 \ifx\PLS@driver\@empty
110   \PackageError{pdflscape}{%
111     Neither pdfTeX, PostScript, nor dvipdfm driver found%
112   }\@ehc
113 \fi

```

2.4 Driver implementation

- `\PLS@AddRotate #1`
it expects the correct rotation number in #1 and implements the adding of the /Rotation entry in the /Page object of the current page.
- `\PLS@RemoveRotate`
it removes a previous /Rotate entry, if necessary.

2.4.1 pdfTeX

Not too nice is the global setting of `\pdfpageattr`. Perhaps this can be changed in future versions.

luatex compat.

```
114 \ifx\pdfpageattr\undefined
115   \ifx\pdfvariable\undefined\else
116     \protected\edef\pdfpageattr{\pdfvariable pageattr}
117   \fi
118 \fi

119 \def\PLS@temp{pdftex}
120 \ifx\PLS@temp\PLS@driver
121   \def\PLS@AddRotate#1{%
122     \ifnum#1=0 %
```

Already the default.

```
123   \else
124     \global\pdfpageattr\expandafter{%
125       \the\pdfpageattr
126       /Rotate #1%
127     }%
128   \fi
129 }%
```

Removes a /Rotate entry.

```
130 \def\PLS@RemoveRotate{%
131   \begingroup
132     \global\pdfpageattr\expandafter{\expandafter}%
133     \expandafter\PLS@RemoveRotate
134     \the\pdfpageattr /Rotate\@nil
135   \endgroup
136 }%
137 \def\PLS@@RemoveRotate#1/Rotate#2\@nil{%
```

Append /Rotate free stuff to `\pdfpageattr`.

```
138   \global\pdfpageattr\expandafter{\the\pdfpageattr#1}%
139   \ifx\\#2\\%
```

Ready, because the detected /Rotate is part of the end marker: /Rotate\@nil

```
140 \else
```

First read in the argument of /Rotate, then continue parsing.

```
141   \afterassignment\PLS@@RemoveRotate
142   \count0=#2\@nil
143   \fi
144 }%
145 \fi
```

2.4.2 PostScript driver

```

146 \def\PLS@temp{dvips}
147 \ifx\PLS@temp\PLS@driver
148   \RequirePackage{atbegshi}%
149   \AtBeginShipout{\PLS@AtBeginShipout}%
150   \let\PLS@AtBeginShipout\empty
151   \def\PLS@AddRotate#1{%
152     \ifnum#1=0 %
153     \else
154       \def\PLS@AtBeginShipout{%
155         \global\setbox\AtBeginShipoutBox\vbox{%
156           \Gin@PS@raw{%
157             [{ThisPage}\string<\string</Rotate #1\string>\string>%
158             /PUT pdfmark%
159           }%
160           \box\AtBeginShipoutBox
161         }%
162       }%
163     \fi
164   }%
165   \def\PLS@RemoveRotate{\let\PLS@AtBeginShipout\empty}%
166 \fi

```

2.4.3 Driver dvipdfm

```

167 \def\PLS@temp{dvipdfm}
168 \ifx\PLS@temp\PLS@driver
169   \RequirePackage{atbegshi}%
170   \AtBeginShipout{\PLS@AtBeginShipout}%
171   \let\PLS@AtBeginShipout\empty
172   \def\PLS@AddRotate#1{%
173     \ifnum#1=0 %
174     \else
175       \def\PLS@AtBeginShipout{%
176         \global\setbox\AtBeginShipoutBox\vbox{%
177           \special{pdf: put @thispage <</Rotate #1>>}%
178           \box\AtBeginShipoutBox
179         }%
180       }%
181     \fi
182   }%
183   \def\PLS@RemoveRotate{\let\PLS@AtBeginShipout\empty}%
184 \fi

```

2.5 Driver independent stuff

The landscape environment is extended by adding the correct `/Rotate` entries.

```

185 \g@addto@macro{\landscape}{\PLS@Rotate{90}}
186 \g@addto@macro{\endlandscape}{\PLS@Rotate{0}}

```

- `\PLS@Rotate` Main macro, that sets the `/Rotate` entry.
 Argument: any TeX number or nothing, that means zero.
 Driver independent.

```

187 \def\PLS@Rotate#1{%
188   \begingroup
1. Check and validate the argument.
189   \PLS@CheckAngle{#1}%
190   \expandafter\endgroup

```

```

2. Remove previous \Rotate entry.
191  \expandafter\PLS@RemoveRotate
3. Add /Rotate entry.
192  \expandafter\PLS@AddRotate\expandafter{\the\count@}%
193 }

\PLS@CheckAngle Validates the rotation angle.
The result is stored in the count register \count@.
Driver independent.
194 \def\PLS@CheckAngle#1{%
Nothing means zero:
195  \ifx\\#1\\%
196    \count@=0 %
197  \else
198    \count@=#1\relax
199  \fi
Normalize to interval -360 < \count@ < 360.
200  \@whilenum\count@>359\do{\advance\count@ -360 }%
201  \@whilenum\count@<-359\do{\advance\count@ 360 }%
Check values: 0, +/-90, +/-180, +/-270
202  \ifnum 1=0\ifnum\count@=0 \else
203    \ifnum\count@=90 \else
204      \ifnum\count@=-90 \else
205        \ifnum\count@=180 \else
206          \ifnum\count@=-180 \else
207            \ifnum\count@=270 \else
208              \ifnum\count@=-270 \else
209                1\fi\fi\fi\fi\fi\fi\relax
210    \PackageError{pdflscape}{%
211      Invalid value \the\count@ space for /Rotate%
212    }\@ehc
213    \count@=0 %
214  \fi
215 }

216 </package>

```

3 Installation

3.1 Download

Package. This package is available on CTAN¹:

[CTAN:macros/latex/contrib/pdflscape/pdflscape.dtx](#) The source file.

[CTAN:macros/latex/contrib/pdflscape/pdflscape.pdf](#) Documentation.

Bundle. All the packages of the bundle ‘pdflscape’ are also available in a TDS compliant ZIP archive. There the packages are already unpacked and the documentation files are generated. The files and directories obey the TDS standard.

[CTAN:install/macros/latex/contrib/pdflscape.tds.zip](#)

TDS refers to the standard “A Directory Structure for TeX Files” ([CTAN:pkg/tds](#)). Directories with `texmf` in their name are usually organized this way.

¹[CTAN:pkg/pdflscape](#)

3.2 Bundle installation

Unpacking. Unpack the `pdflscape.tds.zip` in the TDS tree (also known as `texmf` tree) of your choice. Example (linux):

```
unzip pdflscape.tds.zip -d ~/texmf
```

3.3 Package installation

Unpacking. The `.dtx` file is a self-extracting `docstrip` archive. The files are extracted by running the `.dtx` through plain `TEX`:

```
tex pdflscape.dtx
```

TDS. Now the different files must be moved into the different directories in your installation TDS tree (also known as `texmf` tree):

```
pdflscape.sty → tex/latex/pdflscape/pdflscape.sty  
pdflscape.pdf → doc/latex/pdflscape/pdflscape.pdf  
pdflscape.dtx → source/latex/pdflscape/pdflscape.dtx
```

If you have a `docstrip.cfg` that configures and enables `docstrip`'s TDS installing feature, then some files can already be in the right place, see the documentation of `docstrip`.

3.4 Refresh file name databases

If your `TEX` distribution (`TEX Live`, `mikTEX`, ...) relies on file name databases, you must refresh these. For example, `TEX Live` users run `texhash` or `mktexlsr`.

3.5 Some details for the interested

Unpacking with L^AT_EX. The `.dtx` chooses its action depending on the format:

plain T_EX: Run `docstrip` and extract the files.

L^AT_EX: Generate the documentation.

If you insist on using L^AT_EX for `docstrip` (really, `docstrip` does not need L^AT_EX), then inform the autodetect routine about your intention:

```
latex \let\install=y\input{pdflscape.dtx}
```

Do not forget to quote the argument according to the demands of your shell.

Generating the documentation. You can use both the `.dtx` or the `.drv` to generate the documentation. The process can be configured by the configuration file `ltxdoc.cfg`. For instance, put this line into this file, if you want to have A4 as paper format:

```
\PassOptionsToClass{a4paper}{article}
```

An example follows how to generate the documentation with pdfL^AT_EX:

```
pdflatex pdflscape.dtx  
makeindex -s gind.ist pdflscape.idx  
pdflatex pdflscape.dtx  
makeindex -s gind.ist pdflscape.idx  
pdflatex pdflscape.dtx
```

4 History

[2001/01/15 v0.1]

- First public version, published in `de.comp.text.tex`:
“Re: Querformat, pdfLaTeX und thumbpdf”²

[2001/02/04 v0.2]

- Minor documentation update.
- CTAN.

[2004/05/11 v0.3]

- Support for dvipdfm added.

[2004/05/12 v0.4]

- Bug fix: support for multipage landscape environment for all drivers except for pdftex.

[2006/02/20 v0.5]

- DTX framework.
- LPPL 1.3
- Code is not changed.

[2006/04/24 v0.6]

- Bug fix: `\PLS@RemoveRotate` reinserted for `\PLS@Rotate`.
- Fix for `\PLS@RemoveRotate` (dvips/dvipdfm): `\PLS@EverhShi` hook is cleared.

[2007/04/11 v0.7]

- Line ends sanitized.

[2007/04/17 v0.8]

- Package `atbegshi` replaces `everyshi`.

[2007/10/21 v0.9]

- Driver detection for X_ET_EX added.
- Fix for rotation angles ≤ -360 or ≥ 360 .

[2008/08/11 v0.10]

- Code is not changed.
- URLs updated.

²Url: <https://groups.google.com/group/de.comp.text.tex/msg/e054c5795e52d2b8>

[2016/05/14 v0.11]

- LuaTeX Compatibility

[2019/12/05 v0.12]

- Documentation updates.
- iftex package.

5 Index

Numbers written in italic refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; plain numbers refer to the code lines where the entry is used.

Symbols	
\@ehc	51, 68, 112, 212
\@empty ..	5, 6, 21, 23, 30, 34, 42, 57,
	73, 90, 96, 109, 150, 165, 171, 183
\@nil	134, 137, 142
\@undefined	92, 114, 115
\@whilenum	200, 201
\\"	139, 195
A	
\advance	200, 201
\afterassignment	141
\AtBeginShipout	149, 170
\AtBeginShipoutBox ..	155, 160, 176, 178
B	
\box	160, 178
C	
\count	142
\count@	192,
	196, 198, 200, 201, 202, 203,
	204, 205, 206, 207, 208, 211, 213
\CurrentOption	9, 24, 26
D	
\DeclareOption	8, 22
\do	200, 201
E	
\endlandscape	186
G	
\g@addto@macro	185, 186
\Gin@driver	77
\Gin@PS@raw	92, 94, 96, 156
I	
\ifnum	92, 122, 152, 173,
	202, 203, 204, 205, 206, 207, 208
\ifpdf	41
\ifx	
	23, 30, 34, 42, 46, 57,
	63, 73, 77, 90, 92, 94, 96, 109,
	114, 115, 120, 139, 147, 168, 195
\ifxetex	56
L	
\landscape	185
M	
\MessageBreak	49, 66
N	
\NeedsTeXFormat	2
P	
\PackageError	48, 65, 110, 210
\PackageInfo	44, 59, 79, 104
\PassOptionsToPackage	32, 36
\pdfpageattr	114, 116, 124, 125, 132, 134, 138
\pdfvariable	115, 116
\PLS@RemoveRotate	133, 137, 141
\PLS@AddRotate	121, 151, 172, 192
\PLS@AtBeginShipout	149, 150, 154, 165, 170, 171, 175, 183
\PLS@CheckAngle	189, 194
\PLS@driver	6, 10, 42, 43, 46, 52, 57, 58, 63, 69, 73, 78, 80, 90, 103, 109, 120, 147, 168
\PLS@option	5, 9, 30, 32, 49, 66
\PLS@RemoveRotate	130, 165, 183, 191
\PLS@Rotate	185, 186, 187
\PLS@temp	7, 13, 14, 15, 16, 17, 18, 19, 20, 21, 23, 24, 26, 34, 36, 40, 43, 44, 46, 52, 55, 58, 60, 63, 69, 72, 75, 77, 85, 86, 87, 88, 89, 91, 103, 105, 119, 120, 146, 147, 167, 168
\ProcessOptions	29
\protected	116
\ProvidesPackage	3

	R		T	
\RequirePackage	38, 39, 148, 169	\the	125, 134, 138, 192, 211
	S			
\setbox	155, 176		
\space	60, 80, 102, 105, 211	V	
\special	177	\vbox	155, 176